

# FocusData 1.0 Release Notes

The FocusData software development kit (SDK) is designed to enable the import of data (A-scan, C-scan, and most important inspection parameters) from FocusPC data files into custom software environments. FocusData is mainly used for application-dedicated data presentation and automatic data analysis.

FocusData 1.0R37	2023-06-07
<ul> <li>Fixed bug with ReadAscanSlice function</li> <li>Fixed file A01 without version #</li> </ul>	
FocusData 1.0R36	2022-04-29
Updated concurrently with the FocusPC version	
FocusData 1.0R35	2022-02-16
Updated concurrently with the FocusPC version	
FocusData 1.0R34	2021-07-16
Updated concurrently with the FocusPC version	
FocusData 1.0R33	2021-05-06
Updated concurrently with the FocusPC version	
FocusData 1.0R32	2021-01-15

• Fixed the issue with the installation of FocusData in Windows 10, version 2004

FocusData 1.0R31	2020-10-22
<ul> <li>Updated concurrently with the FocusPC version</li> </ul>	
FocusData 1.0R30	2020-08-28
<ul> <li>Updated concurrently with the FocusPC version</li> </ul>	
FocusData 1.0R29	2020-07-24
<ul> <li>Updated concurrently with the FocusPC version</li> </ul>	
FocusData 1.0R28	2020-05-04
Updated concurrently with the FocusPC version	
FocusData 1.0R27	2020-02-24
Updated concurrently with the FocusPC version	
FocusData 1.0R26	2020-01-31
Updated concurrently with the FocusPC version	
FocusData 1.0R25	2020-03-13
HASP key is no longer required	
FocusData 1.0R24	2019-09-20
Updated concurrently with the FocusPC version	
FocusData 1.0R23	2019-08-08

• Updated concurrently with the FocusPC version

FocusData 1.0R22	2018-08-21
Updated concurrently with the FocusPC version	
FocusData 1.0R21	2018-08-21
Updated concurrently with the FocusPC version	
FocusData 1.0R20	2018-08-21
Updated concurrently with the FocusPC version	
FocusData 1.0R19	
Updated concurrently with the FocusPC version	
FocusData 1.0R17	
Updated the FocusPC, FocusData, and FocusControl documentation	
FocusData 1.0R9	
Updated the FocusPC, FocusData, and FocusControl documentation	
FocusData 1.0R4	
Updated the FocusPC, FocusData, and FocusControl documentation	

#### FocusData 1.0R1

### **Compatible Programming Languages (32-bit and 64-bit)**

- C++
- C#
- VB
- LabVIEW
- MATLAB

## **Supported Operating Systems**

- Microsoft Windows 8
- Microsoft Windows 7 (32-bit and 64-bit)

**Note:** You must have administrator privileges to install FocusData and configure the computer for data acquisition.

### **Computer Requirements**

CPU: Intel Core i7 or Xeon E3RAM: 16 GB (DDR3 or better)

• Data storage drive: SSD

Network adaptor: Gigabit Ethernet card (dedicated for FOCUS PX data acquisition instrument)

• **Display:** 1280 × 1024 or higher

• One USB port for the HASP security hardware key

A keyboard and a pointing device

## **Available Languages**

English